

NVH Source Locator — Kratki priručnik

NVH Source Locator — Kratki priručnik

Jednostranični pregled. Za pune detalje pogledajte **Korisnički priručnik**.

Glavni tijek (2-Sensor, besplatno)

- **Odaberite materijal** — kartica Materials → dodirnite materijal
- **Unesite kalibraciju** na kartici 2-Sensor: - Razmak između senzora (d) - Kašnjenje vremena kalibracije (tCal) — automatski popunjeno iz materijala
- **Unesite događaj** — tEvent i Prvi senzor (A ili B)
- **Pročitajte rezultat** — udaljenost od senzora A



NVH Source Locator
 TDOA Calculator PRO




2-Sensor 3-Sensor 3-Sen+ 4-Sensor 4-Sen+ 3D 3D+ Materials

Pair A-B

Pair A-C

Step 1

Calibration — Speed of Sound

Sensor spacing A-B

-

118

+

cm

External knock time delay

-

471

+

μs

Calculated speed of sound

2505 m/s

Closest: PEEK (2500 m/s)

+ Save as custom material

Step 2

Event Measurement

Event time delay

⊕ trials

-

227

+

μs

Which sensor heard it first?

Sensor A

Calculate Source Location

Kartica 2-Sensor

Sve kartice

Kartica	Izlaz	Pro polja?
2-Sensor	Udaljenost duž linije	Ne (potpuno besplatno)
3-Sensor	X, Y na površini	Da
3-Sen+	X, Y s LSQ-om iz 3 para	Da

4-Sensor	X, Y iz dva para (A–B + C–D)	Da
4-Sen+	X, Y iz 4 senzora, bilo koja pozicija	Da
3D	X, Y, Z iz 4 senzora	Da
3D+	X, Y, Z iz najviše 6 senzora	Da
Materials	Bira  brzine zvuka	Ne
Help	Vodi 	Ne

Postavke se nalaze pod ikonom  (gore desno), a ne kao kartica.

Temperaturna kompenzacija

Postavke → Referentna temperatura, raspon **-40 do +200 °C**.

- **14 metala** ima ugrađenu kompenzaciju (aluminij, , elici, bakar, mjed, bronca, titan, magnezij, olovo, cink, nikal, volfram, željezo, lijevano željezo)
- Materijali bez kompenzacije prikazuju „ref only“
- **Resetira se na 20 °C pri svakom pokretanju aplikacije** (zadani siguran položetak)
- Reprodukcijski unos povijesti vraća izvornu temperaturu

Prečaci

- **Dodir na materijal** → automatski popunjava sva tCāl polja na svim karticama
- **Držite +/-** na brojanim poljima → brzo povećanje
- **Vodoravno povlačenje** po brojnom polju → mijenjanje vrijednosti
- **Prazan/negativan/neispravan unos** → resetira se na 0 pri gubitku fokusa (polje temperature ograničeno na -40/200)
- **Označi materijal zvjezdicom** → premješta ga na vrh izbornika

Pro model

Freemium s zaključanim značajkama (\$19,99):

- Besplatno: kartica 2-Sensor potpuno funkcionalna, bez ograničenja
- Pro: Druge kartice dostupne, ali sa **zlatnim katancima na poljima** koji pri dodiru prikazuju paywall

Pro otključava: 3-Sensor do 3D+, prilagođene materijale, sigurnosno kopiranje/vraćanje, PDF izvješća, označavanje fotografija.



Unlock NVH Pro

Full access to all features

- ✓ 3-Sensor & 4-Sensor triangulation
- ✓ 3D source location (X, Y, Z)
- ✓ Unlimited measurement history
- ✓ Save custom materials
- ✓ Backup and restore
- ✓ PDF reports with photo annotation
- ✓ Temperature compensation across all tabs

Unlock Pro — \$19.99

Have a Google Play promo code?

Looking for a discount code?
[Check the Picoscope Forum →](#)

Questions? support@evdiag.net

Paywall

Izveštaj i sigurnosno kopiranje

Gumb **Ispiši rezultat** na bilo kojem zaslonu rezultata → PDF sa zaglavljem, ulazima, rezultatom, vizualizacijom, fotografijom (ako je snimljena) i podnožjem s temperaturom (kada je kompenzacija aktivna).

Prilagodite zaglavlje u Postavke → Zaglavlje izvještaja.

Sigurnosno kopiranje: Postavke → Sigurnosno kopiranje → dijeljenje u oblak/e-poštom.

Vraćanje: Postavke → Vraćanje → odaberite datoteku kopije.

Vraćanje Pro-a na novom uređaju

Isti Google račun (Android) ili Apple ID (iOS) s kojim ste kupili → Postavke → **Vrati kupnju** → otključava se za nekoliko sekundi.

Automatsko vraćanje događa se tiho kada se vratite u aplikaciju nakon vanjske primjene promotivnog koda.

Brzo rješavanje problema

- **Rezultat izvan raspona?** Provjerite predznak tEvent / Prvi senzor / razmak senzora
- **Pogrešan najbliži materijal?** Referentna temperatura vjerojatno je slučajno postavljena — provjerite postavke
- **Vraćanje kupnje ne uspijeva?** Provjerite isti račun trgovine; ponovno instalirajte ako problem traje
- **Polje postavljeno na 0?** Prazni/negativni unosi automatski se postavljaju pri gubitku fokusa — ponovno unesite vrijednost
- **Nestale tipke step-pera?** Pojavljuju se uz polja s data - step — ponovno pokrenite aplikaciju ako nedostaju
- **Upozorenje o zastarjeloj temperaturi?** Resetira se na 20 pri svakom pokretanju — ponovno postavite za ovu sesiju

Kontakt support@evdiag.net — navedite model uređaja, verziju aplikacije (Postavke → dno) i opis onoga što ste pokušali.